

# Ourexam



---

**H i g h e r   Q u a l i t y**

**B e t t e r   S e r v i c e !**

We offer free update service for one year

[Http://www.ourexam.com](http://www.ourexam.com)

**Exam : 920-340**

**Title : Nortel Software  
Communication System 500  
Rls.2.0 Config**

**Version : Demo**

1.In comparing the types of conferences available with the Software Communication System 500 (SCS500), which conference uses reserved ports?

- A.Scheduled conference
- B.Administrator conference
- C.Meet Me conference
- D.Instant conference

Answer:A

2.Which action is required to configure Hunt Group call scenarios for incoming received digits presented to the Software Communication System 500 (SCS500) system?

- A.Configure user aliases.
- B.Enter the digits from the provider of the digital trunk as the hunt group number.
- C.Determine the call sequence for Hunt Group user extensions.
- D.Specify a Hunt Group Fallback Destination.

Answer:B

3.On which server does the Nortel Software Communication System 500 (SCS500) run?

- A.Intel dual-core E4600 CPU
- B.Standard 1 GB/s Ethernet server
- C.System 5 default server platform
- D.Dell Optiplex 755 server platform

Answer:D

4.Which gateway provides connectivity to the PSTN via digital interfaces (PRI/T1/E1 or BRI)?

- A.AudioCodes MP-118 FXO
- B.Nortel Analog VoIP gateway 4 port FXO
- C.AudioCodes MP-114 FXS
- D.AudioCodes Mediant 1000

Answer:D

5.Click the Exhibit button. Which field do you change to adjust the number of dialpad keys the system accepts before interpreting a user's request?

The screenshot shows the 'Auto Attendant' configuration page. On the left, there is a 'Menu' link and an 'Options' button. The main content area is titled 'Auto Attendant' and contains two sections: 'DTMF Handling' and 'Invalid Response'. The 'DTMF Handling' section has three fields: 'Inter-DTMF Timeout' (value 3, default 3), 'Overall DTMF Timeout' (value 7, default 7), and 'Maximum Number of DTMF tones' (value 10, default 10). The 'Invalid Response' section has a description: 'Configure auto attendant behavior when user enters invalid response or no response is received.' It contains two fields: 'Replay Count' (value 2, default 2) and 'Invalid Response Count' (value 2, default 2).

Section	Field	Value	Default
DTMF Handling	Inter-DTMF Timeout	3	(Default: 3)
	Overall DTMF Timeout	7	(Default: 7)
	Maximum Number of DTMF tones	10	(Default: 10)
Invalid Response	Replay Count	2	(Default: 2)
	Invalid Response Count	2	(Default: 2)

- A.Inter-Dual Tone Multi-frequency (DTMF) Timeout
- B.Maximum Number of DTMF tones
- C.Replay Count
- D.Overall DTMF Timeout

Answer:B